Small amounts of radioactive materials are used in research work at the University of South Florida (USF). Researchers at USF also use radiation-producing equipment such as analytic type x-ray machines.

This general radiation safety information document is being made available to provide information to ensure students, staff, facility and visitors are aware of the potential hazards associated with USF research operations with radioactive material or radiation-producing equipment. In compliance with State of Florida regulations USF requires that a student, staff or facility member complete additional radiological worker training before performing unescorted work assignments as a radiological worker. A radiological worker handles radioactive materials or operates radiation-producing devices.

This document provides general information about radiation, its risks, the controls the University of South Florida implements to ensure the safety of workers, visitors and the environment, and each individual's rights and responsibilities. For specific information about your work area contact your supervisor, or the USF Radiation Safety Office at 813-974-1194.

The type of radiation referred to in this document is ionizing radiation-invisible particles or waves of energy emitted from radioactive atoms or radiation-producing machines. Non-ionizing radiation (e.g., laser light and microwave radiation) presents very different hazards and is controlled through the Non-ionizing Radiation program. The common types of ionizing radiation are alpha, beta, neutron, x-ray, and gamma radiation. Some radioactive atoms (e.g., uranium-238 and thorium-232) are natural; others (e.g., phosphate-32, sulfur-35, and iodine-125) are man-made.

If the energy from the radiation is deposited in a person, he or she receives a radiation dose. Radiation doses are measured in millirems (mrem) or rems. One thousand millirems equal one rem (1000 mrem = 1 rem).

Background radiation is radiation from our natural environment. Everyone is exposed to some amount of background radiation. This exposure primarily comes from cosmic rays, radioactive material in the earth (such as uranium-238), ingestion of naturally occurring radionuclides in food (such as potassium-40), and inhalation of radon gas. In the United States, the average background radiation dose is 300 mrem/yr.

Manufactured sources contribute an additional background radiation dose of approximately 60 mrem /yr. Of this amount, approximately 54 mrem are from medical procedures (e.g., x-rays and certain diagnostic tests). Consumer products such as lantern mantles, smoke detectors, and uranium-glazed pottery contribute roughly 5 mrem /yr. Fallout radiation that is present in our environment contributes less than 1 mrem /yr. Figure 1 shows typical annual radiation doses in the United States.

**In an emergency –**

1. Remain calm.
2. Initiate life saving measures or First Aid, if required.
3. Attend to injured or contaminated persons and remove them from any area where they may receive a radiation dose.
4. Alert people in lab to evacuate.
5. Call Radiation Safety for assistance as soon as possible.

In the event of fire, medical emergency/ or danger to life, health, or the